

Autodesk®
3ds Max® 2010

Autodesk®
3ds Max® Design 2010

Network Licensing Guide

Autodesk® 3ds® Max 2010 Software

© 2009 Autodesk, Inc. All rights reserved. Except as otherwise permitted by Autodesk, Inc., this publication, or parts thereof, may not be reproduced in any form, by any method, for any purpose.

Certain materials included in this publication are reprinted with the permission of the copyright holder.

The following are registered trademarks or trademarks of Autodesk, Inc., in the USA and other countries: 3DEC (design/logo), 3December, 3December.com, 3ds Max, ADI, Alias, Alias (swirl design/logo), AliasStudio, AliasWavefront (design/logo), ATC, AUGI, AutoCAD, AutoCAD Learning Assistance, AutoCAD LT, AutoCAD Simulator, AutoCAD SQL Extension, AutoCAD SQL Interface, Autodesk, Autodesk Envision, Autodesk Insight, Autodesk Intent, Autodesk Inventor, Autodesk Map, Autodesk MapGuide, Autodesk Streamline, AutoLISP, AutoSnap, AutoSketch, AutoTrack, Backdraft, Built with ObjectARX (logo), Burn, Buzzsaw, CAICE, Can You Imagine, Character Studio, Cinestream, Civil 3D, Cleaner, Cleaner Central, ClearScale, Colour Warper, Combustion, Communication Specification, Constructware, Content Explorer, Create>what's>Next> (design/logo), Dancing Baby (image), DesignCenter, Design Doctor, Designer's Toolkit, DesignKids, DesignProf, DesignServer, DesignStudio, DesignStudio (design/logo), Design Web Format, Discreet, DWF, DWG, DWG (logo), DWG Extreme, DWG TrueConvert, DWG TrueView, DXF, Ecotect, Exposure, Extending the Design Team, Face Robot, FBX, Filmbox, Fire, Flame, Flint, FMDesktop, Freewheel, Frost, GDX Driver, Gmax, Green Building Studio, Heads-up Design, Heidi, HumanIK, IDEA Server, i-drop, ImageModeler, iMOUT, Incinerator, Inferno, Inventor, Inventor LT, Kaydara, Kaydara (design/logo), Kynapse, Kynogon, LandXplorer, LocationLogic, Lustre, Matchmover, Maya, Mechanical Desktop, Moonbox, MotionBuilder, Movimento, Mudbox, NavisWorks, ObjectARX, ObjectDBX, Open Reality, Opticore, Opticore Opus, PolarSnap, PortfolioWall, Powered with Autodesk Technology, Productstream, ProjectPoint, ProMaterials, RasterDWG, Reactor, RealDWG, Real-time Roto, REALVIZ, Recognize, Render Queue, Retimer, Reveal, Revit, Showcase, ShowMotion, SketchBook, Smoke, Softimage, Softimage|XSI (design/logo), SteeringWheels, Stitcher, Stone, StudioTools, Topobase, Toxik, TrustedDWG, ViewCube, Visual, Visual Construction, Visual Drainage, Visual Landscape, Visual Survey, Visual Toolbox, Visual LISP, Voice Reality, Volo, Vtour, Wire, Wiretap, WiretapCentral, XSI, and XSI (design/logo).

Trademarks

The following are registered trademarks or trademarks of Autodesk Canada Co. in the USA and/or Canada and other countries: Backburner, Multi-Master Editing, River, and Sparks.

The following are registered trademarks or trademarks of Moldflow Corp. in the USA and/or other countries: Moldflow MPA, MPA (design/logo), Moldflow Plastics Advisers, MPI, MPI (design/logo), Moldflow Plastics Insight, MPX, MPX (design/logo), Moldflow Plastics Xpert.

clothfx™ is a trademark of Size8 Software, Inc. Havok.com™ is a trademark or registered trademark of Havok.com Inc. or its licensors. Intel is a registered trademark of Intel Corporation. mental ray is a registered trademark of mental images GmbH licensed for use by Autodesk, Inc. All other brand names, product names or trademarks belong to their respective holders.

Disclaimer

THIS PUBLICATION AND THE INFORMATION CONTAINED HEREIN IS MADE AVAILABLE BY AUTODESK, INC. "AS IS." AUTODESK, INC. DISCLAIMS ALL WARRANTIES, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE REGARDING THESE MATERIALS.

Contents

Chapter 1	Quick Start to Autodesk Network Licensing	1
	How to Install the Network License Manager	1
	How to Register and Activate a Network License (Previously Network License Activation Utility)	2
	How to Configure a License Server	3
	How to Install and Use SAMreport-Lite (Optional)	4
Chapter 2	Introduction to Autodesk Network Licensing Tools	7
	Network License Manager	7
	System Requirements for the Network License Manager	7
	Register Once Web Site	8
	FLEXnet Configuration Tools	8
	Utilities for License Server Management	9
	The Options File	9
	SAMreport-Lite License Reporting Tool	10
Chapter 3	Plan Your Network Licensing	11
	Plan Your License Server Configuration	11
	Single License Server Model	11
	Distributed License Server Model	12
	Redundant License Server Model	12
	Learn About Your License	13
	License Operation and Availability	13

	License Files	14
	License File Examples	17
	Example of a License File Not Specific to a Product	17
	Example of a License File for a Single or Distributed Server	18
	Example of a License File for a Redundant Server	18
	Example of a License File for Combined Autodesk Product Versions	19
	Example of Additional Parameters in a License File	19
	Package License File Examples	20
	Example of a Package License File for a Single or Distributed Server	21
	Example of a Package License File for a Redundant Server	21
	Example of a Package License File for Combined Autodesk Product Versions	22
	License Types and Behaviors	24
	Heartbeat Signal	24
Chapter 4	Network Licensing Tools	25
	Update FLEXnet from a Previous Version	25
	Obtain the Server Host Name and Host ID Manually	27
	Configure a License Server	28
	Stop and Restart the License Server	30
	Set Up and Use an Options File	31
	Create a Report Log	32
	Configure License Borrowing	33
	Set Up License Timeout	34
	Uninstall the Network License Manager	35
	Glossary	37
	Index	41

Quick Start to Autodesk Network Licensing

1

Setting up network licenses for an Autodesk® product requires careful planning and execution. This section gives you quick, step-by-step instructions about how to set up a network licensed environment, and assumes that you are familiar with the terminology and processes required to set up an Autodesk product to run on a network. If you are not familiar with network licensing, please read the entire *Network Licensing Guide* for further details before you attempt to set up a network license server.

How to Install the Network License Manager

The Network License Manager is used to configure and manage the license servers.

To install your Network License Manager

- 1 In the Autodesk Installation wizard, click Install Tools and Utilities.
- 2 On the Select the Products to Install page, select Autodesk Network License Manager and click Next.
- 3 Review the Autodesk software license agreement for your country or region. You must accept this agreement to proceed with the installation. Choose your country or region, click I Accept, and then click Next.

NOTE If you do not agree to the terms of the license and want to terminate the installation, click Cancel.

- 4 On the Review - Configure - Install page, review your product selection and the current settings. If you do not want to change anything, click

Install. If you want to change the install type or installation path, click Configure.

- 5 On the Select the Installation Type page, select Typical or Custom and accept the default installation path (*C:\Program Files\Autodesk Network License Manager*) or Browse to specify a different path. If you enter a path that does not exist, a new folder is created using the name and location you provide. Click Next.

WARNING Do not install the Network License Manager on a remote drive. When you install the Network License Manager files, you must provide a path to a local drive. You must specify the drive letter; the universal naming convention (UNC) is not permitted.

- 6 On the Configuration Complete page, click Configuration Complete to return to the confirmation page.
- 7 On the Review - Configure - Install page, click Install.
- 8 When the Installation Complete page displays, click Finish.

How to Register and Activate a Network License (Previously Network License Activation Utility)

You can obtain network licenses over the Internet at <https://registeronce.autodesk.com>.

To register and activate your network license online:

- 1 Go to <https://registeronce.autodesk.com>.
- 2 Login to your account. If you do not have an account, click Create User ID and fill in the necessary information.
- 3 You can accept or reject your current account information. Then select the account you will be using for your network license.
- 4 Enter the Serial Number and Product Key. You can find these numbers on the DVD case or in the e-mail you received when ordering online.
- 5 Choose the Network Server Type. (Click the ? button for a description of each type.) Enter all server host names and IDs.

- 6 On the Product Registration & Activation page you can see your license file. You can also save the LIC version to your computer and print out the license file information.

NOTE It is recommended that you save your license file to *C:\Program Files\Autodesk Network License Manager\License*.

How to Configure a License Server

You configure a license server so that you can manage the Autodesk product licenses you received when you visited the “Register Once” web site at <https://registeronce.autodesk.com>. Configure the license server with the *lmttools.exe* utility.

To configure your license server

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 2 In the LMTOOLS program, on the Service/License File tab, make sure the Configure Using Services option is active.
- 3 Click the Config Services tab.
- 4 In the Service Name list, select the service name you want to use to manage licenses.

By default, the service name is *Flexlm Service 1*. If FLEXnet® is managing other software on your computer in addition to Autodesk, you can change the service name to avoid confusion. For example, you can rename *Flexlm Service 1* to *Autodesk Server1*.

NOTE If you have more than one software vendor using FLEXnet® for license management, the Service Name list contains more than one option. Make sure that only one Autodesk service is listed.

- 5 In the Path to Lmgrd.exe File field, enter the path to the Network License Manager daemon (*lmgrd.exe*), or click Browse to locate the file.
By default, this daemon is installed in the *C:\Program Files\Autodesk Network License Manager* folder.
- 6 In the Path to the License File box, enter the path to your license file, or click Browse to locate the file.
This is the path to the license file obtained during registration at <https://registeronce.autodesk.com>.
- 7 In the Path to the Debug Log File box, enter a path to create a debug log, or click Browse to locate an existing log file.
It is recommended that you save to the *C:\Program Files\Autodesk Network License Manager* folder. The log file must have a *.log* file extension. For new log files, you must enter the *.log* extension manually.
- 8 To run *lmgrd.exe* as a service, select Use Services.
- 9 To start *lmgrd.exe* automatically when the system starts, select Start Server at Power Up.
- 10 Click Save Service to save the new configuration under the service name you selected in step 4. Click Yes when prompted if you would like to save the settings to the service.
- 11 Click the Start/Stop/Reread tab and do one of the following:
 - If a service has not yet been defined for Autodesk, click Start Server to start the license server.
 - If a service for Autodesk is already defined and running, click ReRead License File to refresh the Network License Manager with any changes made to the license file or Options file.The license server starts running and is ready to respond to client requests.
- 12 Close *lmtools.exe*.

How to Install and Use SAMreport-Lite (Optional)

SAMreport-Lite is a reporting tool that helps you track network license usage. With SAMreport-Lite technology from Acreesso™ Software, you can monitor client usage for Autodesk network licensed products.

To learn more about installing and using SAMreport-Lite, see the *SAMreport-Lite User's Guide*; click the Documentation link at the lower left corner of the Installation wizard or see the Autodesk product's Help system.

Introduction to Autodesk Network Licensing Tools

2

Autodesk Network licensing tools include the Network License Manager, the Register Once web site at <https://registeronce.autodesk.com>, the FLEXnet configuration tools, and SAMreport-Lite. Each tool is described in the sections that follow.

Network License Manager

The Network License Manager is used to configure and manage the license servers. When creating a deployment, the Installation wizard prompts you for information about the license manager, such as license server model and server name.

For more information about deploying an Autodesk product from a network location, see the *Network Administrator's Guide*, by clicking the Documentation link at the lower left corner of the Installation wizard.

System Requirements for the Network License Manager

Make sure that your network license server meets the minimum recommended requirements. See the following table for hardware and software requirements.

NOTE Not all products support all operating systems. See your product's *Network Administrator's Guide* for supported operating systems.

Hardware and software requirements for the network license server

Hardware/software	Requirement	Notes
Operating system	Windows Vista® 32-bit SP1 Windows Vista 64-bit SP1 Windows® XP 32-bit SP3 Windows XP 64-bit SP2 Windows 2003 R2 Server Edition Windows 2003 Server Edition Windows 2000 Server Edition*	The Network License Manager supports Ethernet network configurations only. *If you use a Windows 2000 Server, you must manually install the Network License Manager located in your product's install folder: <i>CDROM1\X86\support\NLM\en-US\NLM.msi</i> .
Computer/processor	Pentium® III or higher 450 Mhz (minimum)	
Network interface card	Compatible with existing Ethernet network infrastructure	The Network License Manager supports multiple network interface cards, but at least one must be an Ethernet card.
Communication protocol	TCP/IP	The Network License Manager uses TCP packet types.

Register Once Web Site

With the Register Once web site at <https://registeronce.autodesk.com>, you can obtain licenses over the Internet, which saves time and effort in setting up a network licensed Autodesk product. License information is saved.

FLEXnet Configuration Tools

The Network License Manager uses FLEXnet® license management technology from Acreso Software. FLEXnet provides administrative tools that help to simplify management of network licenses. You can use FLEXnet tools to monitor network license status, reset licenses lost to a system failure, troubleshoot license servers, and update existing license files on the fly.

Utilities for License Server Management

FLEXnet provides two utilities for managing the license server. These tools are located in the *C:\Program Files\Autodesk Network License Manager* folder.

lmtools.exe Provides a Microsoft® Windows graphical user interface for managing the license server.

lmutil.exe Provides a set of command line options for managing the license server.

You can use *lmtools.exe* or *lmutil.exe* to perform the following server management tasks:

- Start, stop, and restart the server.
- Configure, update, and reread the license file.
- Diagnose system or license problems.
- View server status, including active license status.

The Options File

Another component of FLEXnet is the Options file. You create this file to set specific configuration options. For information about creating and using an options file, see [Set Up and Use an Options File](#) on page 31.

Use the Options file to set parameters for the following server-related features:

Report log file A compressed, encrypted file is created that generates accurate usage reports on license activity for use by SAMreport-Lite. For more information about SAMreport-Lite, see the *SAMreport-Lite User's Guide*, which you can access on the Documentation tab of the menu browser.

License borrowing If your Autodesk product supports the license borrowing feature, you can allow users to borrow an Autodesk product license from a network license server so that they can use the product without being connected to the license server. A license can be borrowed for a limited time.

License timeout With license timeout, you can set a timeout period on your license server for one Autodesk product at a time. When set, license timeout returns a license to the license server when a connection with the workstation is lost, or if a license is checked out but the Autodesk product is idle on a workstation for longer than the timeout period you define.

License timeoutall With license timeoutall, you can set a timeout period on your license server that applies to all Autodesk products installed on your computer. When set, license timeout returns a license to the license server when a connection with the workstation is lost, or if a license is checked out but the Autodesk product is idle on a workstation for longer than the timeout period you define.

For more information about configuration options, see [Set Up and Use an Options File](#) on page 31.

For specific information about using FLEXnet configuration tools, see the FLEXnet documentation by navigating to *C:\Program Files\Autodesk Network License Manager\Docs\FlexUser\LicenseAdministration.pdf*.

SAMreport-Lite License Reporting Tool

While not part of the network installation, a version of SAMreport called SAMreport-Lite is available to help you track network license usage. With SAMreport-Lite technology from Acreso Software, you can monitor client usage for Autodesk network licensed products.

SAMreport-Lite generates usage reports in various output formats including HTML, text, and Report Interchange Format. For more information about the SAMreport-Lite features and for instructions on installing SAMreport-Lite, see the *SAMreport-Lite User's Guide*.

NOTE You can install SAMreport-Lite and access the *SAMreport-Lite User's Guide* from the Autodesk product menu browser.

For additional information about SAMreport-Lite, and for updates and fixes for this feature, visit the Autodesk website at:

www.autodesk.com/samreportlite

Plan Your Network Licensing

3

This section contains information that you need to know before you set up a network license server. The section includes information about supported license server models, license operation and availability, network license file definitions and parameters, license file examples, license types and behaviors, and the license server heartbeat signal.

Plan Your License Server Configuration

You must decide which license server model to use for managing your Autodesk product licenses on a server. Autodesk supports the following network license server models:

- Single license server model
- Distributed license server model
- Redundant license server model

Single License Server Model

In the single license server model, the Network License Manager is installed on a single server, so license management and activity is restricted to this server. A single license file represents the total number of licenses available on the server.

Advantages of the Single License Server Model

- Because all license management takes place on a single server, you have just one point of administration and one point of failure.

- Of the three license server models, this configuration requires the least amount of maintenance.

Disadvantage of the Single License Server Model

- If the single license server fails, the Autodesk product cannot run until the server is back online.

Distributed License Server Model

In the distributed license server model, licenses are distributed across more than one server. A unique license file is required for each server. To create a distributed license server, you must run the Network License Manager on each server that is part of the distributed server pool.

Advantages of the Distributed License Server Model

- Servers can be distributed across a wide area network (WAN); they do not need to exist on the same subnet.
- If one server in the distributed server pool fails, the licenses on the remaining servers are still available.
- If you need to replace a server in the distributed server pool, you do not need to rebuild the entire pool.
- Server replacement is easier than in a redundant server pool, where you must reactivate the entire pool.

Disadvantage of the Distributed License Server Model

- If a server in the distributed server pool fails, the licenses on that server are unavailable.

Redundant License Server Model

In the redundant license server model, you use three servers to authenticate a single license file. One server acts as the master, while the other two provide backup if the master server fails. With this configuration, licenses continue to be monitored and issued as long as at least two servers are still functional. The license file on all three servers is the same. You must install the Network License Manager on each server.

In the redundant license server model, all servers must reside on the same subnet and have consistent network communications. (Slow, erratic, or dial-up connections are not supported.)

Advantage of the Redundant License Server Model

- If one of the three servers fails, all licenses that are managed in the server pool are still available.

Disadvantages of the Redundant License Server Model

- If more than one server fails, no licenses are available.
- All three servers must reside on the same subnet and have reliable network communications. The redundant server pool does not provide network fault tolerance.
- If one of the three servers is replaced, the complete redundant server pool must be rebuilt.
- If your Autodesk product supports license borrowing and licenses are borrowed from a redundant license server pool, you must restart the license server after you stop the Network License Manager.

Learn About Your License

In this section, you learn about license operation and availability, the license file, license types and behaviors, and the heartbeat signal.

License Operation and Availability

When you start an Autodesk product, the product determines the server from which it should try to obtain a license. The product then requests a license through the TCP/IP network protocol to the license server.

If the number of available licenses has not been exceeded on the license server, the Network License Manager assigns a license to the workstation. A product session then starts on the workstation, and the number of available licenses on the license server is reduced by one.

Likewise, when you exit a product, the Network License Manager frees a license for another user. If you run multiple sessions of an Autodesk product on an individual workstation, only one license is used. When the last session is closed, the license is freed.

The following three processes manage the distribution and availability of licenses:

- **License manager daemon** (*lmgrd.exe*). Handles the original contact with the application, and then passes the connection to the vendor daemon. The *lmgrd.exe* daemon is used to communicate with the vendor daemon only; *lmgrd.exe* does not authenticate or dispense licenses, but rather passes user requests to the vendor daemon. By using this approach, a single *lmgrd.exe* daemon can be used by multiple software vendors to provide license authentication. The *lmgrd.exe* daemon starts and restarts the vendor daemons as needed.
- **Autodesk vendor daemon** (*adskflex.exe*). Tracks the licenses that are checked out and the workstations that are using them. Each software vendor has a unique vendor daemon to manage vendor-specific licensing. As its name implies, the *adskflex.exe* vendor daemon is specific to Autodesk products.

NOTE If the *adskflex.exe* vendor daemon terminates for any reason, all users lose their licenses until *lmgrd.exe* restarts the vendor daemon or the problem causing the termination is resolved.

- **License file.** A text file that has vendor-specific license information.

License Files

The network license file you receive from Autodesk contains licensing information required for a network installation. You obtain license file data when you register your Autodesk product.

The license file contains information about network server nodes and vendor daemons. It also contains an encrypted digital signature that is created when Autodesk generates the file.

The license file is located in a network location that you specify in the Deployment wizard. That network location must be accessible to every user who runs the product from a network installation.

The following table defines each license file parameter.

Definitions of license file parameters

Line	Parameter	Definition	Example
SERVER	Host Name	Host name of the server where the Network License Manager resides	LABSERVER
	Host ID	Ethernet address of the server where the Network License Manager resides	03D054C0149B
USE_SERVER	[None]		
VENDOR	Vendor Daemon	Name of the server-side Autodesk vendor daemon	<i>adskflex.exe</i>
	Port Number	Network port number reserved and assigned for use only by Autodesk products running the Autodesk vendor daemon	port=2080
PACKAGE	Name	Name of feature code group	<i>SERIES_1</i>
	Version	Internal version number reference	1.000
	COMPONENTS	List of feature codes supported in the package	COMPONENTS="526000REVIT_9_OF\ 51200ACD_2007_OF\ 513001IN- VBUN_11_OF"
	OPTIONS		OPTIONS=SUITE
	SUPERSEDE	Replacement for any existing Increment line of the same feature code from any license files on the same license server that have a date earlier than the defined Issue Date	SUPERSEDE
	SIGN	Encrypted signature used to authenticate the attributes of the license file	SIGN=0 SIGN2=0
INCREMENT	Feature Code	Product supported by the license file	51200ACD_2007_OF

Definitions of license file parameters

Line	Parameter	Definition	Example
	Expiration Date	Amount of time the licenses are available	permanent
	Number of Licenses	Number of licenses supported by the license file	25
	VENDOR_STRING	License usage type and license behavior of the product that is supported by the license file	COMMERCIAL
	BORROW	Definition of the license borrowing period for the licenses defined under the same increment line. In this example, the maximum period that licenses can be borrowed is 4320 hours (180 days), unless otherwise noted (for example, BORROW=2880 means that licenses can be borrowed for a maximum of 2880 hours, or 120 days). License borrowing is disabled when this parameter is absent in the license file.	BORROW=4320
	DUP_GROUP	Definition of multiple license requests when the same user and same host share the same license	DUP_GROUP=UH
	ISSUED	Date that the license file was generated by Autodesk	15-jul-2006
	Serial Number	Serial number of the Autodesk product	123-12345678
	SIGN	Encrypted signature used to authenticate the attributes of the license file	SIGN=6E88EFA8D44C

License File Examples

License file examples are provided in this document to help you understand how the license files work for your particular network setup. Autodesk provides a standard license file for individual products and a license file with additional parameters for products that are sold both individually and as part of a product set.

- **Standard License File.** If you purchase one or more individual products that are not offered as part of a suite of products, you receive a standard license file.
- **Standard License File with Additional Parameters.** If you purchase Autodesk products that are included in a product set and are also sold as an individual product, you receive a standard license file with additional parameters included in the license file. The additional parameters define the sequence for license usage so that the individual product license is used before the license for the product set.

Autodesk license file examples include a license file not specific to a product, completed license files for single, distributed, and redundant server models, a combined product version license file, and an example of additional parameters added to a standard license file.

Example of a License File Not Specific to a Product

Here is an example of the contents of a license file and the parameters associated with each line:

```
SERVER ServerName HostID
USE_SERVER
VENDOR adskflex port=portnumber
INCREMENT feature_code Adskflex Version ExpDate NumberofLicenses
\
VENDOR_STRING=UsageType:Behavior BORROW=4320 SUPERSEDE \
DUP_GROUP=DupGrp ISSUED=IssueDate SN=SerialNumber SIGN= \
```

Example of a License File for a Single or Distributed Server

Here is an example of a completed license file for a single or distributed license server model:

```
SERVER XXHP0528 0019bbd68993
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1393 \
  E368 816E D417 C1CD 7DBD 7B90 1354 D6F0 48FE EBB8 9C84 C3AF \
  7D79 BEE1 0181 0655 76FF 996C B707 14B5 D4DE A3FE 0B2D 2D36 \
  057C A579 7866 26BF 44E2" SIGN2="1280 943B 53A7 9B93 E00B D967
  \
  D821 BD37 BE6D B78A F074 B223 88AA 242C DD0A 1292 D56F 4108 \
  62CD FA35 E365 0736 A011 7833 8B35 7BFF DAD8 34A8 452F 2EB4"
```

Example of a License File for a Redundant Server

Here is an example of a completed license file for a redundant license server model:

```
SERVER CCN12378042 001cc4874b03 27005
SERVER XXHP0528 0019bbd68993 27005
SERVER CCN12378043 001cc4874b10 27005
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=10-Jan-2008 SN=123-12345678 SIGN="11C4 \
  CA79 07FC 7AD0 409A 6E04 6E98 D76C 197C 0416 076C B211 1CDD \
  D0AB 698B 16BF 7A0E D4F8 1CFE 2985 644F 64CD CECE 0DDB 5951 \
  3262 7C31 13A8 F08F 55B2" SIGN2="19A6 FDA3 2ED5 5301 8675 7B81
  \
  1B0E 451B 19F1 1A99 C8E9 CBA6 8CB3 6AC3 8B38 1519 13F2 2373 \
  82AE 55E5 1A25 4952 4458 F3A2 6F28 D25D 1DC0 E066 209B 0953"
```

NOTE The redundant server model requires the addition of a port number (the default is 27005) for each server.

Example of a License File for Combined Autodesk Product Versions

You can combine a license file for different releases of the same Autodesk product or for different Autodesk products, and run all products from one license server. For example, you can combine a license file for AutoCAD 2009 with license files for Maya® 2009 and AutoCAD Map.

Here is an example of the contents of a combined license file for AutoCAD 2008 and AutoCAD 2009:

```
SERVER XXHP0528 0019bbd68993
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1393 \
  E368 816E D417 C1CD 7DBD 7B90 1354 D6F0 48FE EBB8 9C84 C3AF \
  7D79 BEE1 0181 0655 76FF 996C E707 14B5 D4DE A3FE 0B2D 2D36 \
  057C A579 7866 26BF 44E2" SIGN2="1280 943B 53A7 9B93 E00B D967
\
  D821 BD37 BE6D B78A F074 B223 88AA 242C DD0A 1292 D56F 4108 \
  62CD FA35 E365 0736 A011 7833 8B35 7BFF DAD8 34A8 452F 2EB4"
INCREMENT 54600ACD_2008_0F adskflex 1.000 permanent 3 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1E6E \
  4B61 5712 4766 92A0 6782 9EF4 3F47 56A1 1F38 6DE8 C0C7 90AC \
  7289 152E 0EA2 CC0D 3F10 577A 0489 CEB6 10D5 FBCC B552 0C9D \
  5966 91A6 59F0 2788 FACE" SIGN2="1DDF 3B9D 3392 71D5 AB08 7E05
\
  8497 111E 092F 0E54 8DC2 2BED 17C2 2CC1 981B 0EC2 BC15 8F00 \
  C79A ABFD 2136 BABA 2EDF E941 EA53 32C6 597F F805 5A8A 599A"
```

Example of Additional Parameters in a License File

For Autodesk products that are included in a product set and are also sold as an individual product, licenses are allocated based on a sequence of priorities defined in the license file. For those products, information similar to the following example appears in a license file:

```
SERVER Server1 1a34567c90d2
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 54600ACD_2008_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2007 SN=123-12345678 SIGN="0247 \
  45D6 87C4 27A5 7F9E F24A ED3D 61E4 6B3B CC5C AD77 B865 9EA8 \
  3D62 0792 0F67 19E7 57E7 FAFA A48B D582 335A EC16 1FE5 B70D \
  76AB 6488 61CC DE5E F5B7" SIGN2="09FD 0850 7CF1 F447 9F05 9FA3
  \
  2A0A 38D6 83FC 1746 F3F5 5A72 6250 E002 DE0B 0E6E F88C AC95 \
  136F 87F2 A945 E4C4 A97F 44B5 74EE 83F3 3F3E 1579 B981 8994"
```

Package License File Examples

Autodesk offers a package license file option, which allows you use of a set of products that are packaged and sold together. The package license file contains a set number of licenses for four different versions of your software. Running an instance of any one of the versions uses one license in the package. Packaged license files support prior versioning for subscription users. Package license files operate under the following guidelines:

- Package license files come with the current version of the software and three previous versions of the same product.
- License files may be combined with license files for different products. For more information about combining license files, see [Example of a License File for Combined Autodesk Product Versions](#) on page 19.
- Package license files cannot be combined with non-package license files for product versions contained in the package. For example, you cannot combine a *Autodesk Product 2009* package license file with a regular license file for *Autodesk Product 2008*, *2007*, or *2006*.
- Both the `PACKAGE` and `INCREMENT` sections of the license are required for licensing to work properly. When you combine license files, be sure to include both of these sections.
- License borrowing, option files, and licensing cascading work the same for package licenses as they do for regular license files.
- A new license file will supersede an older license file.

The following sections provide package license file examples for single, distributed, and redundant license servers, and combined Autodesk product versions.

Example of a Package License File for a Single or Distributed Server

Here is an example of a completed license file for a single or distributed license server model:

```
SERVER Server1 1a34567c90d2
USE_SERVER
VENDOR adskflex port=2080
PACKAGE SERIES_1 adskflex 1.000 COMPONENTS="54700REVIT_2009_0F \
54600ACD_2009_0F 51300INVBUN_11_0F" OPTIONS=SUITE SUPERSEDE \
ISSUED=09-Jan-2008 SIGN="1707 9EAC CBCB 2405 692E 4A89 \
AA26 30CC 2AC2 D6B3 A61B AB5E 492E 3EBD 0B48 4E75 193A DA82" \
FC45 C009 E360 944A 14BA E99C 9B24 5A1B 4A44 083A BE5F 3827 \
SIGN2="004A FC90 AB47 3F6B 59BC 0E6D 6681 6971 A76A BA52 98E2
\
5671 26B3 0E78 791B 109F 0591 7DC3 F09F 4D8D 4FB7 E341 4A03 \
CD68 1D77 27F8 8555 9CF7 DEDD 9380"
INCREMENT SERIES_1 adskflex 1.000 permanent 100 \
VENDOR_STRING=commercial:permanent BORROW=4320 DUP_GROUP=UH \
SUITE_DUP_GROUP=UHV SN=123-12345678 SIGN="1707 9EAC CBCB \
692E 4A89 FC45 C009 E360 944A 14BA E99C 9B24 5A1B 4A44 BE5F \
3827 AA26 30CC 2AC2 D6B3 A61B AB5E 492E 3EBD 0B48 DA82" \
SIGN2="004A FC90 AB47 3F6B 59BC 0E6D 6681 6971 A76A BA52 \
5671 26B3 0E78 791B 109F 0591 7DC3 F09F 4D8D 4FB7 E341 4A03 \
CD68 1D77 27F8 8555 9CF7 DEDD 9380"
```

Example of a Package License File for a Redundant Server

Here is an example of a completed license file for a redundant license server model:

```

SERVER 1a34567c90d2 27005
SERVER 2a34567c90d2 27005
SERVER 3a34567c90d2 27005
USE_SERVER
VENDOR adskflex port=2080
PACKAGE 64300ACD_F adskflex 1.000 COMPONENTS="57600ACD_2009_0F \
54600ACD_2008_0F 51200ACD_2007_0F 48800ACD_2006_0F" \
OPTIONS=SUITE SUPERSEDE ISSUED=27-May-2008 SIGN="1092 05D8 \
A206 276B 2C84 EFAD ACA5 C54B 68A4 653E C61F 31DE C8CE B532 \
CFBB 0006 5388 347B FDD6 A3F4 B361 7FD4 CDE4 4AAC 0D11 B0EF \
4B44 BFD6 3426 97DD" SIGN2="0670 B01A D060 0069 FF25 F1CD D06B
\
314E E7C9 3552 5FFA 4AC7 28A7 C897 F56A 19BB FB1C 754E 6704 \
DEEA AC4E F859 2E9B 64B6 ODD0 9CCE 9556 269F EAC0 2326"
INCREMENT 64300ACD_F adskflex 1.000 permanent 50 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH SUITE_DUP_GROUP=UHV ISSUED=27-May-2008 \
SN=399-99999999 SIGN="1B5B 8D70 4CAD 32E5 9CA2 82E0 5C47 291C
\
35AB 9B9C 5B3E 5067 F61B 4139 1B32 0716 1FD3 5105 A991 B78E \
9D1E 63AB BC23 0D1E B70C 2A05 E1C1 F605 ABB1 2EA8" SIGN2="01D6
\
31F5 2951 4500 E5C8 058F 7490 9789 9EF4 CBED DA27 5F06 6780 \
9033 2018 0C3B E1E0 3580 E60E C2BB B4AB 8D6A 4245 3059 8CA6 \
2EFE DFAE 027F 2ABE 3F2B"

```

Example of a Package License File for Combined Autodesk Product Versions

Here is an example of a completed license file for combined Autodesk product versions:

```

SERVER servername 123456789111
USE_SERVER
VENDOR adskflex port=2080
PACKAGE 64300ACD_F adskflex 1.000 COMPONENTS="57600ACD_2009_OF \
54600ACD_2008_OF 51200ACD_2007_OF 48800ACD_2006_OF" \
OPTIONS=SUITE SUPERSEDE ISSUED=25-Jun-2008 SIGN="03EF DE18 \
8046 0124 4EA4 6953 F82D 3169 7C24 D0DE E58E 8168 FFA3 D891 \
B43B 08D8 7E7F C6ED CBCC FE2A BB0A 4566 C2AE F1C1 D373 8348 \
E6E3 884A E398 1C78" SIGN2="07AC D696 8844 D19F AB00 8B75 53A3
\
2F76 91DF AED0 3231 1506 0E6B ADC6 C3B8 1797 93B5 9756 8C0F \
8811 56E6 B2BA 0523 FE2E 82B7 1628 076F 173B F37C 7240"
INCREMENT 64300ACD_F adskflex 1.000 permanent 2 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH SUITE_DUP_GROUP=UHV ISSUED=25-Jun-2008 \
SN=399-99999999 SIGN="1CCB E88D B819 8604 06FA 9AEE 42F1 CBEA
\
37B9 3CFA A0A8 697F 9CB1 8354 6256 05ED 69D4 D2FF D512 6A2E \
D5DD B722 EF5B 3172 BA95 4625 F8D3 DD24 BB39 6A58" SIGN2="0DFE
\
FA6F C378 20E0 2622 BE52 B434 F99F 2681 2B93 64F2 CE0C 7F4A \
7024 B3D1 051A 6920 72BD DE35 8920 E6A1 C8D6 AF23 7BE7 CC91 \
6916 70B1 9E80 AB07 1644"
PACKAGE 64800INVPRO_F adskflex 1.000 \
COMPONENTS="59600INVPRO_2009_OF \
55300INVPRO_2008_OF 51400INVPRO_11_OF 49000INVPRO_10_OF" \
OPTIONS=SUITE SUPERSEDE ISSUED=25-Jun-2008 SIGN="1306 5990 \
F8A1 56FB 1D8A 9DA7 D6AE 8E9E F6EC 2862 367A 36E2 C5FB E6E1 \
4AAA 0128 8C2D 95FD 09B2 ABA1 6F98 A0A3 70DE 3220 6835 7E51 \
3849 9D81 8BDC 9DC1" SIGN2="0021 AA08 F2E7 8AEB 5345 341A 7E42
\
3001 B8C5 DFC2 6EB8 87C5 C04A AE43 A10F 1DA1 EF8A F0FA 10F5 \
AC81 1E22 789F A18D 650F 6BBB 563A BDA5 DD1C 82EC 27F6"
INCREMENT 64800INVPRO_F adskflex 1.000 permanent 2 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH SUITE_DUP_GROUP=UHV ISSUED=25-Jun-2008 \
SN=399-99999966 SIGN="0BE4 51F4 570C DC48 5E66 F952 629E EDF0
\
019C 6FF7 0509 1FF0 D4FB 3B16 1981 073F 31EC A241 8CB3 8782 \
E655 00C6 E097 D5EF B0D8 67D3 199D 699D 2E09 B16F" SIGN2="1254
\
3E37 0CE4 F42D B7CD 858C 92FC A963 5274 770F 9354 FE29 E117 \
205D C632 0C4E AEC0 7501 9D9E FFE8 D84D F154 16A1 E120 339A \

```

License Types and Behaviors

Autodesk supports dynamic product usage and license behaviors. This means that you can purchase a specific type of behavior with a specific license and change that license at a later date without having to uninstall and reinstall the Autodesk product.

License types include the following:

- **Commercial.** A license for a product that was purchased commercially.
- **Not for Resale.** A license for a product that is not sold commercially. Not for Resale products are for evaluation or demonstration purposes only and may not be used for commercial or production use.
- **Educational (EDU)/Institution.** A license designed specifically for educational institutions.
- **Student Portfolio.** A license for students who are using an Autodesk product as part of their curriculum.

License behaviors are as follows:

- **Permanent.** Enables permanent use of an Autodesk product.
- **Term Extendable.** Enables access to an Autodesk product for a limited time. The term can be extended at any time.
- **Term Non-Extendable.** Enables an Autodesk product for a limited time. The term cannot be extended.

Heartbeat Signal

When an Autodesk product is running, it communicates with the license server at regular intervals using a communication method known as the “heartbeat” signal. If the heartbeat signal is lost, the server tries to reconnect. If the server cannot reconnect, the user receives a license error.

If the product stops working because it has lost a connection to the server, you must shut down the product, and then restart it. If the problem causing the original loss of the heartbeat signal is resolved and there are available licenses on the server, the program can be restarted.

Network Licensing Tools

4

This section includes information for updating FLEXnet, and installing and configuring the Autodesk Network License Manager on a network.

Update FLEXnet from a Previous Version

This release of Autodesk products and later require FLEXnet version 11.5 or later. If you are currently using a version of FLEXnet that is earlier than 11.5, you need to upgrade to version 11.5 or later.

NOTE If the server where you plan to install the Autodesk Network License Manager has FLEXnet installed for another product, make sure that the version of *lmgrd.exe* is the most current version.

To determine what version of FLEXnet is installed, you need to verify the version of the following files:

- *lmgrd.exe*
- *lmtools.exe*
- *lmutil.exe*
- *adskflex.exe*

To verify the version of *lmutil.exe*, *lmtools.exe*, or *adskflex.exe*

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 2 In *lmtools.exe*, click the Utility tab.
- 3 On the Utility tab, enter the location of the file, or click the Browse button to locate the file and click Open. The file location should look something like this:
C:\Program Files\Autodesk Network License Manager\lmutil.exe
- 4 On the Utility tab, click Find Version.
The version number of the file you selected is displayed. If necessary, use the following procedure to update your version of FLEXnet.

To update FLEXnet

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Back up your license files.
- 2 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 3 In the LMTOOLS program, click the Start/Stop/Reread tab.
- 4 On the Start/Stop/Reread tab, click Stop Server.
- 5 Close *lmtools.exe*.
- 6 Note the location where the Network License Manager is installed and then uninstall the Network License Manager. For details about uninstalling the Network License Manager, see [Uninstall the Network License Manager](#) on page 35.
- 7 Install the Network License Manager. For details about installing the Network License Manager to the same location as the previous version, see [Install the Autodesk Network License Manager](#).

- 8 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 9 In the LMTOOLS program, click the Start/Stop/Reread tab.
- 10 On the Start/Stop/Reread tab, click Start Server.
- 11 Close *lmtools.exe*.

Obtain the Server Host Name and Host ID Manually

If you cannot use the Register Once web site at <https://registeronce.autodesk.com> to obtain your server host name and host ID, you can acquire this information manually. Use the Windows command prompt or run the *lmtools.exe* utility. If you use *lmtools.exe*, do not run it on a remote workstation. Autodesk uses the server host name, host ID, and product serial number to generate a license file.

To obtain the host name and ID using the Windows command prompt

- 1 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Accessories ► Command Prompt.
 - (Windows Vista) Click Start ► All Programs ► Accessories ► Command Prompt.
- 2 At the Windows command prompt, enter the following command, and then press ENTER:
ipconfig /all
- 3 Locate the Host Name line, and write down the host name.
- 4 Locate the Physical Address line. Write down the physical address *without* the dashes. This is your twelve-character host ID.

NOTE If your server has more than one network adapter, select the one that corresponds to a physical network adapter. To determine which adapters are physical: in the Windows command prompt, enter **ipconfig /all**, and then view the Description field above each physical address. If there is more than one physical network adapter, it does not matter which one you use. Devices such as VPN adapters, PPP adapters, and modems are not valid.

- 5 Close the Windows command prompt.

To obtain the host name and ID using *lmtools.exe*

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 2 In the LMTOOLS program, click the Systems Settings tab.
- 3 On the Systems Settings tab, locate the Computer/Hostname box. Copy the host name and paste the information into a text editor.
- 4 Locate the Ethernet Address box. The Ethernet address is the host ID. It consists of twelve characters. Write down the information. If your Ethernet address is more than twelve characters, write down the first twelve characters only.

NOTE If your server has more than one Ethernet adapter, select one that corresponds to a physical network adapter.

- 5 Close *lmtools.exe*.

Configure a License Server

You configure a license server so that you can manage the Autodesk product licenses you received at <https://registeronce.autodesk.com>. Configure the license server with the *lmtools.exe* utility.

To configure your license server

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 2 In the LMTOOLS program, on the Service/License File tab, make sure the Configure Using Services option is active.
- 3 Click the Config Services tab.
- 4 In the Service Name list, select the service name you want to use to manage licenses.

By default, the service name is *Flexlm Service 1*. If FLEXnet® is managing other software on your computer in addition to Autodesk, you can change the service name to avoid confusion, for example, you can rename *Flexlm Service 1* to *Autodesk Server1*.

NOTE If you have more than one software vendor using FLEXnet® for license management, the Service Name list contains more than one option. Make sure that only one Autodesk service is listed.

- 5 In the Path to Lmgrd.exe File field, enter the path to the Network License Manager daemon (*lmgrd.exe*), or click Browse to locate the file.
By default, this daemon is installed in the *C:\Program Files\Autodesk Network License Manager* folder.
- 6 In the Path to the License File box, enter the path to your license file, or click Browse to locate the file.
This is the path to the license file obtained at <https://registeronce.autodesk.com>.
- 7 In the Path to the Debug Log File box, enter a path to create a debug log, or click Browse to locate an existing log file.
It is recommended that you save to the *C:\Program Files\Autodesk Network License Manager* folder. The log file must have a *.log* file extension. For new log files, you must enter the *.log* extension manually.
- 8 To run *lmgrd.exe* as a service, select Use Services.

- 9 To start *lmgrd.exe* automatically when the system starts, select Start Server at Power Up.
 - 10 Click Save Service to save the new configuration under the service name you selected in step 4. Click Yes when prompted if you would like to save the settings to the service.
 - 11 Click the Start/Stop/Reread tab and do one of the following:
 - If a service has not yet been defined for Autodesk, click Start Server to start the license server.
 - If a service for Autodesk is already defined and running, click ReRead License File to refresh the Network License Manager with any changes made to the license file or Options file.
- The license server starts running and is ready to respond to client requests.
- 12 Close *lmtools.exe*.

Stop and Restart the License Server

Before you can perform any system maintenance on your license server, you must stop the license server. When you have completed maintenance, you can restart the license server.

To stop the license server

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 2 In the LMTOOLS program, on the Service/License File tab, select the Configure Using Services option.
- 3 Select the service name for the license server you want to start manually.
- 4 Click the Start/Stop/Reread tab.
- 5 On the Start/Stop/Reread tab, click Stop Server.
- 6 Close *lmtools.exe*.

To restart the license server

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 2 In the LMTOOLS program, on the Service/License File tab, select the Configure Using Services option.
- 3 Select the service name for the license server you want to start manually.
- 4 Click the Start/Stop/Reread tab.
- 5 On the Start/Stop/Reread tab, click Start Server to restart the license server.

Set Up and Use an Options File

With an Options file, you set configuration options for managing licenses on each license server that you set up. An Options file sets parameters that the license file reads and the *lmgrd* program executes.

If you want to have the same license behavior on some or all of your license servers, you must save the same Options file to each of those license servers. If you want to specify different license behavior on different license servers, you must create an Options file for each license behavior. You must save each Options file to the server where you want specific license behavior.

NOTE For Options file changes to take effect on a license server, you must save the Options file, and then use *lmtools.exe* to reread the license file.

With an Options file, you can do the following:

- [Create a Report Log](#) on page 32
- [Configure License Borrowing](#) on page 33
- [Set Up License Timeout](#) on page 34

Here is an example of the contents of an Options file:

```
REPORTLOG=c:\test\report.rl
```

```
BORROW_LOWWATER Autodesk_f1 3
```

```
TIMEOUT Autodesk_f1 7200
```

You can also set up advanced license parameters, such as reserving a license, restricting license usage, or defining groups of users. To learn more about setting advanced Options file parameters, see the FLEXnet documentation in the *C:\Program Files\Autodesk Network License Manager\docs\FlexUser* folder.

To create an Options file

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Open a text editor, enter the parameters you want, and then save the document as a file named *adskflex.opt* to the same location where you saved the license file.

NOTE Make sure you save the file with the extension *.opt*. The default extension *.txt* is not recognized by the Network License Manager.

- 2 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 3 (Windows) In the program, on the Start/Stop/Reread tab, click ReRead License File.
- 4 (Windows) Close *lmtools.exe*.

Create a Report Log

In the Options file, you can create a report log file that is used with SAMreport-Lite.

To create a report log

- 1 In a text editor, open the Options file, *adskflex.opt*.
- 2 In the Options file, enter the following syntax on its own line (with REPORTLOG entered in uppercase, as shown):
REPORTLOG [+]report_log_path

For example (Windows), the syntax `REPORTLOG +"c:\My Documents\report.rl"` means that a report log named *report.rl* is located in the folder *c:\My Documents*.

NOTE Path names that contain spaces must be enclosed in quotation marks.

In the `REPORTLOG` syntax, “[+]” means that entries to the log file you create are appended rather than replaced each time the Network License Manager is restarted. (It is recommended that you use this option so that you retain a history of log entries.)

Configure License Borrowing

If your Autodesk product supports the license borrowing feature, you can use the Options file to configure license borrowing options. For example, you can define the maximum number of licenses that cannot be borrowed from your network at any one time. In addition, you can define which users can borrow an Autodesk product license. Licenses are borrowed per user, not per machine.

NOTE If your Autodesk product supports license borrowing, and licenses are borrowed from a redundant license server pool, you must restart the license server after you stop the Network License Manager.

At the end of a borrow period, the borrowed license is automatically disabled on the user's computer and becomes available again on the license server. Users can also return a license before a borrow period has ended.

To set license borrowing parameters

- 1 In the Options file, enter the following syntax on its own line (with `BORROW_LOWWATER` entered in uppercase, as shown):

`BORROW_LOWWATER feature_code n`

In the `BORROW` syntax, “feature_code” is the name of the product in the license file, and “n” is the number of licenses that cannot be borrowed.

For example, the syntax `BORROW_LOWWATER Autodesk_f1 3` means that for the product `Autodesk_f1`, three licenses cannot be borrowed from the license server.

- 2 Enter the following syntax on the next line (with `MAX_BORROW_HOURS` entered in uppercase, as shown):

`MAX_BORROW_HOURS feature_code n`

In this syntax, “n” is the number of hours that a license can be borrowed. For example, the syntax `MAX_BORROW_HOURS Autodesk_f1 360` means that for product `Autodesk_f1`, licenses can be borrowed for 360 hours, or 15 days.

NOTE Licenses are borrowed in increments of 24 hours only. Any number that is more than a 24-hour increment is not used. For example, the number 365 would be rounded down to 360 hours, or 15 days.

For more information about setting up the license borrowing feature, see the FLEXnet documentation in the `C:\Program Files\Autodesk Network License Manager\Docs\FlexUser` folder.

NOTE Users can borrow a license in an Autodesk product by clicking the Tools menu ► License Borrowing, or by entering **borrowlicense** on the Autodesk product command line. Help for this feature is available in the Borrow a License for *[Autodesk Product]* window and in `C:\Program Files\[Autodesk Product]\Help\adsk_brw.chm`.

Set Up License Timeout

License timeout is set in the Options file to determine how long a product session can be idle before the license is reclaimed by the license server. When you set this flag in the Options file, a user's license is reclaimed by the license server if the product is idle on a workstation for more than the timeout period you define.

If a user's license is lost because of the idle timeout, the product attempts to claim a new license once the user uses the product again. If no license is available, the user can save work before the product shuts down.

You can set individual license timeouts for each Autodesk product on your computer by using the `TIMEOUT` parameter or you can set one license timeout for all Autodesk products on your computer by using the `TIMEOUTALL` parameter.

To set license timeout parameters

- For individual Autodesk products: In the Options file, enter the following syntax on its own line (with `TIMEOUT` entered in uppercase, as shown):
TIMEOUT feature_code n

In the TIMEOUT syntax, “feature_code” is the name of the product (referred to in the INCREMENT line in the license file), and “n” is the number of seconds before an inactive license is reclaimed by the license server.

For example, the syntax TIMEOUT Autodesk_f1 7200 means that for the product Autodesk_f1, the license timeout period is set for 7200 seconds, or two hours.

- For all Autodesk products: In the Options file, enter the following syntax on its own line (with TIMEOUTALL entered in uppercase, as shown):

TIMEOUTALL n

In the TIMEOUTALL syntax, “n” is the number of seconds before an inactive license is reclaimed by the license server.

For example, the syntax TIMEOUTALL Autodesk 7200 means that for all Autodesk products, the license timeout period is set for 7200 seconds, or two hours.

For more information about using the license timeout feature, see the FLEXnet documentation in the *C:\Program Files\Autodesk Network License Manager\Docs\FlexUser* folder.

Uninstall the Network License Manager

You can uninstall the Network License Manager from the license server. When you uninstall the Network License Manager, licenses are no longer available to your users.

To uninstall the Network License Manager

- 1 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 2 In the LMTOOLS program, click the Start/Stop/Reread tab.
- 3 On the Start/Stop/Reread tab, click Stop Server.
- 4 Close *lmtools.exe*.
- 5 In the Windows Control Panel, double-click Add/Remove Programs.

- 6 In the Add/Remove Programs window, click Autodesk Network License Manager. Click Remove.
- 7 If prompted, restart your computer.

NOTE You must manually delete files that you created for use with the Network License Manager (such as log files, license files, and the Options file). They are not automatically deleted when you uninstall the Network License Manager.

Glossary

adskflex.exe The Autodesk vendor daemon used with the FLEXnet license technology. This daemon keeps track of the Autodesk licenses that are checked out and the workstations that are using the licenses.

ADSKFLEX_LICENSE_FILE In a distributed license server configuration, the environment variable used to point a workstation to the distributed license servers.

borrowed license A license that allows you to use an Autodesk product for a limited period of time without having to buy a separate license or have network access to the license server.

daemon A program that runs continuously in the background of a computer. The daemon handles requests from the computer and then forwards the requests to other programs or processes. The Network License Manager uses two daemons: the vendor daemon (*adskflex.exe*) and the license manager daemon (*lmgrd.exe*).

debug log file A file used with FLEXnet to log connection activity (such as license failure or starting and stopping) between the Network License Manager and the workstation.

deployment The files and folders created on a server and used by workstations to install Autodesk programs.

distributed server A license server configuration option in which several servers are used to manage license distribution. Each distributed license server has a unique license file and a fixed number of licenses. If one distributed license server fails, the other servers are still able to distribute their licenses.

Ethernet address See *host ID*.

feature code A license file parameter that represents the product that is supported by that license file.

FLEXnet The Acrecco Software license management technology implemented in the Autodesk family of products.

heartbeat signal The communication signal between the Network License Manager and the workstation to verify that the workstation is accessible and has an active Autodesk product session running.

host ID The unique hardware address of a network adapter. Also known as *Ethernet address* or *physical address*.

host name The TCP/IP name associated with a computer. FLEXnet technology uses the host name as a parameter; the host name must be distinguished from the NetBIOS (server) name.

idle A state of inactivity in your product that prompts a network license server to reclaim a license. Inactivity is due to no mouse or keyboard activity and no commands, LISP expressions, menu macros, or scripts in progress for the period of time that is defined in the Options file. See also *license timeout*.

JRE (Java Runtime Environment) A program that is required to run Java programs. This program must be installed with SAMreport-Lite.

license file A file used with FLEXnet that controls the number of available seats. This file must be in ASCII plain text format.

license server A server that contains the Network License Manager.

license timeout A feature that allows you to set up a timeout period on your license server to automatically return an idle license to the server so that it is available for use again.

licpath.lic In both single and redundant server configurations, the file used to point the workstation to the FLEXnet license server. *Licpath.lic* is located in the root installation folder.

lmgrd.exe The license manager daemon. This daemon handles the original contact with the program, and then passes the connection to the vendor daemon, *adskflex.exe*.

lmtools.exe A graphical user interface utility used to administer the FLEXnet license technology. (*Lmutil.exe* is the command line version of this utility.)

Lmutil.exe A command line utility used to administer the FLEXnet license technology. (*Lmtools.exe* is the graphical user interface version of this utility.)

master daemon See *lmgrd.exe*.

network license installation A type of installation that requires you to install and run the Network License Manager from a network server. You must install and configure the Network License Manager before clients can run the Autodesk product.

Network License Manager The technology used by Autodesk for network license management.

Options file The file used by FLEXnet to control license manager parameters, such as reserving licenses and creating report logs used with SAMreport-Lite.

physical address See *host ID*.

redundant server A license server configuration option in which three servers are used to administer licenses. The redundant servers share a license file and a pool of licenses. The redundant server pool remains functional as long as two of the three servers are running and communicating with each other.

Register Once Web Site A web site that allows network administrators to license and authorize network versions of an Autodesk product over the Internet found at <https://registeronce.autodesk.com>.

report log file A file used with FLEXnet and SAMreport-Lite. This log file provides information about network license usage. The Options file creates the report log.

SAMreport-Lite A version of Aceso Softwares's SAMreport tool. SAMreport-Lite is included on the Autodesk product discs.

vendor daemon See *adskflex.exe*.

workstation A desktop computer used by an individual user on a network.

Index

A

- activating
 - network license 2
- AdLM (Network License Manager) 7
- adskflex.exe (Autodesk vendor daemon) 14, 25
- Autodesk License Manager 7
- Autodesk vendor daemon 25

B

- borrowing licenses 33

C

- cascading license files 19
- Commercial licenses 24
- configuring
 - license borrowing 33
 - license servers 3, 28, 31

D

- daemons
 - license manager daemons 14
 - vendor daemons 14
 - versions of 25
- distributed license server model
 - about 12
 - license file example 18

E

- Educational (EDU)/Institution
 - licenses 24
- Ethernet address 27

F

- FLEXnet tools
 - about 8
 - Options file 31
 - updating 25

G

- glossary 39

H

- hardware requirements
 - Network License Manager 7
- heartbeat signals 24
- host IDs 27
- host names 27

I

- installation
 - Network License Manager 1
 - SAMreport-Lite 4
- Installation wizard 7

L

- license borrowing 33
- license files
 - about 14
 - additional parameters in 19
 - combined products 19
 - examples 17
 - package examples 20
- license manager daemon 14, 25
- license servers
 - configuring 3, 28, 31
 - heartbeat signals 24

- host IDs and host names 27
- management utilities 9
- models 11
- Network License Manager 7
- stopping and restarting 30
- types of 11
- license timeout 34
- licenses
 - about 13
 - assigning 13
 - availability 13
 - behaviors (term limits) 24, 31
 - FLEXnet tools 8
 - glossary 39
 - license files 14
 - license servers 3, 28
 - license timeout 34
 - Network License Manager 7
 - Register Once website 8
 - reports 10
 - types of 24
- lmgrd.exe (license manager daemon) 14, 25
- lmtools.exe utility 25, 27
- lmutil.exe utility 25
- log files
 - report log files 32

M

- Microsoft Windows
 - configuring license servers 3, 28

N

- network license
 - registering 2
- network license installations
 - license behaviors 31
 - license borrowing 33
 - license timeout 34
 - planning 11
 - tools and utilities 7, 25
 - types of 24
- Network License Manager
 - about 7

- assigning licenses 13
- glossary 39
- installing 1
- license server models 11
- uninstalling 35
- Not for Resale licenses 24

O

- Options file (FLEXnet tools) 31

P

- package license files 20–22
- Permanent licenses 24
- physical address 27

R

- redundant license server model
 - about 12
 - license file example 18
 - package license files 21
- Register Once website 8
- registering
 - network license 2
- report log files 32
- reports
 - SAMreport-Lite License Reporting tool 10

S

- SAMreport-Lite
 - about 10
 - installing 4
- servers
 - host IDs and host names 27
 - license servers 3, 7, 28
 - stopping and restarting 30
- single license server model
 - about 11
 - license file example 18
 - package license files 21

- software requirements
 - Network License Manager 7
- Student Portfolio licenses 24
- system requirements
 - Network License Manager 7

T

- TCP/IP names 27
- Term Extendable licenses 24
- Term Non-Extendable licenses 24
- timeouts 34

U

- updating
 - FLEXnet tools 25

V

- vendor daemons 14, 25

W

- Windows
 - configuring license servers 3, 28

